Setting properties in C++/WinRT is done by a function call, but you need to call the function the right way

devblogs.microsoft.com/oldnewthing/20221028-00

October 28, 2022



For people transitioning to C++/WinRT from other languages, a common beginner mistake is setting properties incorrectly. Here are the ways of accessing a Windows Runtime property in various languages.

Language	Read a property	Write a property
C#	oldValue = o.ActiveWidget;	o.ActiveWidget = newValue;
VB	oldValue = o.ActiveWidget	o.ActiveWidget = newValue
JavaScript	oldValue = o.activeWidget;	o.activeWidget = newValue;
Python	old_value = o.active_widget	o.active_widget = new_value
C++/CX	oldValue = o->ActiveWidget;	o->ActiveWidget = newValue;
C++/WinRT	<pre>oldValue = o.ActiveWidget();</pre>	o.ActiveWidget(newValue);

Notice the odd one out in the above list.¹ Everybody uses the assignment operator to set a property, except C++/WinRT, which uses a function call.

If you're used to the other languages, you may incorrectly interpret the rule that "property access is a function call" People transitioning to C++/WinRT from other languages are tempted to write

```
o.ActiveWidget() = newValue;
```

in a misguided attempt to set the property to a new value. What this actually does is fetch the current value of the property, and then assign the new value to the temporary. It's a lot of work with nothing to show for it, and then you scratch your head wondering why the attempt to update the property appears to have been ignored.

I <u>tried to update C++/WinRT to deny assignment to most types of rvalues</u>, rendering the above a compile-time error, but the change <u>had to be reverted for compatibility reasons</u>.

There's no real value to creating a temporary only to assign a new value to it. You may as well just create the temporary with the desired value, and then use it.

```
// Pointless
DoSomething(o.ActiveWidget() = newValue);

// Just do this
DoSomething(Widget(newValue));

// Or possibly even just
DoSomething(newValue);
```

¹ Rust/WinRT also uses function calls to access properties:

Language	Read a property	Write a property
Rust/WinRT	<pre>old_value = o.active_widget();</pre>	<pre>o.set_active_widget(new_value);</pre>

However, it doesn't suffer from the same problem as C++/WinRT, because Rust disallows assignment to rvalues (known as *value expressions* in Rust-speak).

```
// error E0070: Invalid left-hand side of assignment
o.active_widget() = new_value;
```

The problem of assigning to a temporary is peculiar to C++.

Raymond Chen

Follow

